

Chapter 9. Stress relaxation

Stress relaxation is a special property of non-Newtonian fluids

- ▶ not in elastic solids
- ▶ not in viscous fluids


Hence

non-Newtonian $\neq \frac{1}{2}$ elastic solid + $\frac{1}{2}$ viscous fluid

Important relaxation time τ of stress/microstructure.

Linear visco-elasticity – common to all fluid models

μ_0 solvent viscosity, G elastic modulus, τ relaxation time.



- ▶ Early viscosity μ_0
- ▶ Steady state viscosity $\mu_0 + G\tau$
- ▶ Takes τ to build up to steady state
- ▶ steady deformation = shear rate $\gamma \times$ memory time τ

NB steady flows are unsteady Lagrangian.

E.G. linear visco-elasticity for Oldroyd-B

Microstructure A :

$$\frac{DA}{Dt} - \nabla u^T \cdot A - A \cdot \nabla u + \frac{1}{\tau}(A - I) = 0$$

Stress σ :

$$\sigma = -pI + 2\mu_0 E + G(A - I)$$

Weak flow: $\nabla u \ll \frac{1}{\tau}$, so $A = I + a$ with $|a| \ll 1$

$$\frac{Da}{Dt} + \frac{1}{\tau}a = 2E$$


Start up:

$$a = \dot{\gamma}\tau(1 - e^{-t/\tau}) \quad \sigma = \mu_0\dot{\gamma} + G\dot{\gamma}\tau(1 - e^{-t/\tau})$$

Stopping:


$$a = \dot{\gamma}\tau e^{-t/\tau} \quad \sigma = G\dot{\gamma}\tau e^{-t/\tau}$$

Contraction flow – Lagrangian unsteady




Numerical Oldroyd-B

$\frac{\Delta P}{Stokes}$



Experiments

$\frac{\Delta P}{Stokes}$



Δp scaled by Stokes using steady-state viscosity $\mu_0 + G\tau$.

But if flow fast, lower pressure drop from early-time viscosity μ_0 .

Oldroyd-B has no big increase in Δp , and no big upstream vortex

