

### Summary of Vector Calculus

The following results apply to any (suitably differentiable) scalar field  $\phi(\mathbf{x})$  and vector fields  $\mathbf{u}(\mathbf{x})$  and  $\boldsymbol{\omega}(\mathbf{x})$ . They all have important applications in fluid mechanics.

**Derivatives of a vector field:**

$$\begin{aligned} \text{div } \mathbf{u} &\equiv \nabla \cdot \mathbf{u} = \frac{\partial u_i}{\partial x_i} && \text{has one component and is a scalar} \\ \text{curl } \mathbf{u} &\equiv (\nabla \wedge \mathbf{u})_i = \epsilon_{ijk} \frac{\partial u_k}{\partial x_j} && \text{has three components and is a vector} \\ \text{grad } \mathbf{u} &\equiv (\nabla \mathbf{u})_{ij} = \frac{\partial u_i}{\partial x_j} && \text{has nine components and is a 2nd-rank tensor} \end{aligned}$$

**Two identities:**

$$\text{curl grad } \phi = \nabla \wedge \nabla \phi \equiv 0 . \quad \text{div curl } \mathbf{u} = \nabla \cdot \nabla \wedge \mathbf{u} \equiv 0 .$$

**Two vector triple products:**

$$\begin{aligned} \mathbf{u} \wedge (\nabla \wedge \mathbf{u}) &= \frac{1}{2} \nabla u^2 - (\mathbf{u} \cdot \nabla) \mathbf{u} \\ \nabla \wedge (\mathbf{u} \wedge \boldsymbol{\omega}) &= (\boldsymbol{\omega} \cdot \nabla) \mathbf{u} - (\mathbf{u} \cdot \nabla) \boldsymbol{\omega} + \mathbf{u} (\nabla \cdot \boldsymbol{\omega}) - \boldsymbol{\omega} (\nabla \cdot \mathbf{u}) \end{aligned}$$

**Divergence Theorem (Gauss):** If  $V$  is a simply connected domain with surface  $S$  and outward normal  $\mathbf{n}$  then

$$\int_V \frac{\partial f}{\partial x_i} dV = \int_S f n_i dA ,$$

where  $f$  can be a scalar, a vector or a general tensor. If  $f$  is the vector  $u_i$ , the LHS (with summation over  $i$ ) is the *volume* integral of  $\nabla \cdot \mathbf{u}$  and the RHS is the *area* integral of  $\mathbf{u} \cdot \mathbf{n}$

**Stokes' Theorem:** If  $\Gamma$  is a closed curve spanned by the surface  $S$  then

$$\oint_{\Gamma} \mathbf{u} \cdot d\mathbf{l} = \int_S (\nabla \wedge \mathbf{u}) \cdot d\mathbf{S}$$

**Derivative in a direction:**  $\mathbf{u} \cdot \nabla$  represents the rate of change in the direction of  $\mathbf{u}$  of whatever it is applied to. Note that if  $\mathbf{u} \cdot \nabla$  is applied to a vector field in curvilinear coordinates then it cannot simply be applied to each coordinate of the vector field since the basis vectors  $\mathbf{e}_i$  also vary with position.

**Curl in curvilinear coordinates** ( $\xi_1, \xi_2, \xi_3$ ):

$$\nabla \wedge \mathbf{u} = \frac{1}{h_1 h_2 h_3} \begin{vmatrix} h_1 \mathbf{e}_1 & h_2 \mathbf{e}_2 & h_3 \mathbf{e}_3 \\ \frac{\partial}{\partial \xi_1} & \frac{\partial}{\partial \xi_2} & \frac{\partial}{\partial \xi_3} \\ h_1 u_1 & h_2 u_2 & h_3 u_3 \end{vmatrix} ,$$

where:  $h_1 = 1, h_2 = r, h_3 = 1$  in cylindrical polars ( $r, \theta, z$ ); and  
 $h_1 = 1, h_2 = r, h_3 = r \sin \theta$  in spherical polars ( $r, \theta, \varphi$ ).

## Cylindrical coordinates $(r, \theta, z)$

**Grad, div and Laplacian:**

$$\begin{aligned}\nabla\phi &= \left( \frac{\partial\phi}{\partial r}, \frac{1}{r} \frac{\partial\phi}{\partial\theta}, \frac{\partial\phi}{\partial z} \right) \\ \nabla \cdot \mathbf{u} &= \frac{1}{r} \frac{\partial(r u_r)}{\partial r} + \frac{1}{r} \frac{\partial u_\theta}{\partial\theta} + \frac{\partial u_z}{\partial z} \\ \nabla^2\phi &= \frac{1}{r} \frac{\partial}{\partial r} \left( r \frac{\partial\phi}{\partial r} \right) + \frac{1}{r^2} \frac{\partial^2\phi}{\partial\theta^2} + \frac{\partial^2\phi}{\partial z^2}\end{aligned}$$

**Volume and line elements, and normal to cylinder:**

$$\begin{aligned}dV &= r \, dr \, d\theta \, dz & \mathbf{dl} &= (dr, r \, d\theta, dz) \\ \mathbf{n} &= (\cos\theta, \sin\theta, 0)\end{aligned}$$

**Stream function for 2D flow ( $u_z = \partial/\partial z = 0$ ):**

$$\mathbf{u} = \left( \frac{1}{r} \frac{\partial\psi}{\partial\theta}, -\frac{\partial\psi}{\partial r}, 0 \right)$$

**Stream function for axisymmetric flow ( $u_\theta = \partial/\partial\theta = 0$ ):**

$$\mathbf{u} = \left( -\frac{1}{r} \frac{\partial\Psi}{\partial z}, 0, \frac{1}{r} \frac{\partial\Psi}{\partial r} \right)$$

---

## Spherical coordinates $(r, \theta, \varphi)$

*Note that  $r$  and  $\theta$  denote different quantities in cylindrical and spherical polars.*

**Grad, div and Laplacian:**

$$\begin{aligned}\nabla\phi &= \left( \frac{\partial\phi}{\partial r}, \frac{1}{r} \frac{\partial\phi}{\partial\theta}, \frac{1}{r \sin\theta} \frac{\partial\phi}{\partial\varphi} \right) \\ \nabla \cdot \mathbf{u} &= \frac{1}{r^2} \frac{\partial(r^2 u_r)}{\partial r} + \frac{1}{r \sin\theta} \frac{\partial(\sin\theta u_\theta)}{\partial\theta} + \frac{1}{r \sin\theta} \frac{\partial u_\varphi}{\partial\varphi} \\ \nabla^2\phi &= \frac{1}{r^2} \frac{\partial}{\partial r} \left( r^2 \frac{\partial\phi}{\partial r} \right) + \frac{1}{r^2 \sin\theta} \frac{\partial}{\partial\theta} \left( \sin\theta \frac{\partial\phi}{\partial\theta} \right) + \frac{1}{r^2 \sin^2\theta} \frac{\partial^2\phi}{\partial\varphi^2}\end{aligned}$$

**Volume and line elements, and normal to sphere:**

$$\begin{aligned}dV &= r^2 \sin\theta \, dr \, d\theta \, d\varphi & \mathbf{dl} &= (dr, r \, d\theta, r \sin\theta \, d\varphi) \\ \mathbf{n} &= (\cos\theta, \sin\theta \cos\varphi, \sin\theta \sin\varphi)\end{aligned}$$

**Stream function for axisymmetric flow ( $u_\varphi = \partial/\partial\varphi = 0$ ):**

$$\mathbf{u} = \left( \frac{1}{r^2 \sin\theta} \frac{\partial\Psi}{\partial\theta}, -\frac{1}{r \sin\theta} \frac{\partial\Psi}{\partial r}, 0 \right)$$